

AD 70154

Armed Services Technical Information Agency

**Reproduced by
DOCUMENT SERVICE CENTER
KNOTT BUILDING, DAYTON, 2, OHIO**

Because of our limited supply, you are requested to
RETURN THIS COPY WHEN IT HAS SERVED YOUR PURPOSE
so that it may be made available to other requesters.
Your cooperation will be appreciated.

NOTICE: WHEN GOVERNMENT OR OTHER DRAWINGS, SPECIFICATIONS OR OTHER DATA ARE USED FOR ANY PURPOSE OTHER THAN IN CONNECTION WITH A DEFINITELY RELATED GOVERNMENT PROCUREMENT OPERATION, THE U. S. GOVERNMENT THEREBY INCURS NO RESPONSIBILITY, NOR ANY OBLIGATION WHATSOEVER; AND THE FACT THAT THE GOVERNMENT MAY HAVE FORMULATED, FURNISHED, OR IN ANY WAY SUPPLIED THE SAID DRAWINGS, SPECIFICATIONS, OR OTHER DATA IS NOT TO BE REGARDED BY IMPLICATION OR OTHERWISE AS IN ANY MANNER LICENSING THE HOLDER OR ANY OTHER PERSON OR CORPORATION, OR CONVEYING ANY RIGHTS OR PERMISSION TO MANUFACTURE, USE OR SELL ANY PATENTED INVENTION THAT MAY IN ANY WAY BE RELATED THERETO.

UNCLASSIFIED

AD No. 72 154

ASTIA FILE COPY

FC

Translation 51

BUOYANCY OF SEA ICE
(Plovuchest' morskogo l'da)

by
V. S. Nazarov

Severnyi Morskoi Put', 11, p. 62-63,
Leningrad (1939)
SIPRE Abstract SIP 1041

Translated from the Russian by
N. Zikeev,

SIPRE Bibliography Project,
Library of Congress

SNOW ICE AND PERMAFROST RESEARCH ESTABLISHMENT
Corps of Engineers, U. S. Army
Wilmette, Illinois

BUOYANCY OF SEA ICE

by
V. S. Nazarov

Sea ice has frequently been used in recent times for transport and handling of freight, but the safe bearing capacities of the ice are not known.

Let us make a first approximation of the buoyancy of sea ice.

The buoyancy of sea ice is inversely proportional to its density, i. e., the buoyancy of sea ice decreases with increase in density. This is true only for winter ice, i. e., ice which has not been affected by melting. Ice which has been affected by melting throughout its entire mass is called spring ice. The buoyancy of spring ice is directly proportional to its density, i. e., its buoyancy increases with density. The following examples confirm this.

The density of winter ice varies from 0.900-0.924 [g/cm³]. One dm³ of ice with a density of 0.900 loses its buoyancy with a load of 100 g; 1 dm³ of ice with a density of 0.924 loses its buoyancy with a load of 6*g, etc. Spring ice has densities from 0.839-0.900. The decrease in density of spring ice occurs as a result of melting and the formation inside the ice of cavities filled with water. The use of a correction factor for the volume of the water inside the ice increases the density of spring ice to 0.977-0.993, i. e., 1 dm³ loses its buoyancy with a 7-g load. Movement over this type of ice or displacement of loads on its surface is not practical.

The densities of polar sea ice vary extremely, from 0.839-0.924 according to actual measurements.

The table of safe surface loading of sea ice has been calculated from these data. In using the table one must remember that it gives maximum loading values, and loads must be decreased according to the safety factor required. A 10% decrease is sufficient for stationary loads.

*Translator's note: Should be 76.

BUOYANCY OF SEA ICE

Table of Safe Surface Loading of Sea Ice

Ice thickness (cm)	Load Limit (kg/m ²)	
	Winter ice	Spring ice
10	7.6	0.8
20	15.2	1.6
30	22.8	2.4
40	30.4	3.2
50	38.0	4.0
60	45.6	4.8
70	53.2	5.6
80	60.8	6.4
90	68.4	7.2
100	76.0	8.0
110	83.6	8.8
120	91.2	9.6
130	98.8	10.4
140	106.4	11.2
150	114.0	12.0
160	121.6	12.8
170	129.2	13.6
180	136.8	14.4
190	144.4	15.2
200	152.0	16.0
300	228.0	24.0